
2.1.2 Pairing through LauncherPlus Pairing Utility

The LauncherPlus Pairing Utility allows you to pair your LauncherPlus directly from this PC software. Please follow the instructions provided in the subsequent list.


- 1. Launch the LauncherPlus Pairing Utility from a Windows PCs.
- 2.Plug the LauncherPlus into a PC's USB-C port.
- 3.On the main page, click the Select button in the Novo devices tab.



There are two ways to designate the target Novo devices: Auto Detect and Manual Input


Auto Detect

- The utility will automatically detect and display the target Novo device's IP address.




Manual Input:

- Fill in the required IP address, SSID, Security protocol, and Password, then click Save.



- 1. Click Select or Save to connect to the target Novo device.
- 2. Once the connection is established, the screen will return to the Main page.
- 3. The Pair button in the Pairing tab will now be available to click.



- 4. Click the Pair button to start pairing LauncherPlus and the Novo device.
- 5. Once the pairing process is finished, you need to unplug the LauncherPlus and close the utility.

