


2.1.2 Pairing through LauncherPlus Pairing Utility

The **LauncherPlus Pairing Utility** allows you to pair your LauncherPlus directly from this PC software. Please follow the instructions provided in the subsequent list.


1. Launch the **LauncherPlus Pairing Utility** from a Windows PCs.
2. Plug the LauncherPlus into a PC's USB-C port.
3. On the main page, click the Select button in the Novo devices tab.



There are two ways to designate the target Novo devices: Auto Detect and Manual Input

Auto Detect

– The utility will automatically detect and display the target Novo device's IP address.



The screenshot shows a web interface titled "Novo devices" with a green header. Below the header, there are two tabs: "Auto Detect" (which is selected and underlined) and "Manual Input". The main content area is a white box with a light green border. Inside this box, there is a label "Novo devices IP address" followed by the IP address "192.168.125.24". Below this, there is a bullet point that reads: "• Please ensure that your laptop and the targeted Novo devices are on the same network". In the bottom right corner of the white box, there is a button labeled "Select".

Manual Input:

– Fill in the required IP address, SSID, Security protocol, and Password, then click Save.

< Novo devices

Auto Detect Manual Input

Novo devices IP address

10.13.7.4

Novo devices name or wireless AP SSID

Novo-0365F

Security protocol

None


None

WPA2

Clear

Save

1. Click Select or Save to connect to the target Novo device.
2. Once the connection is established, the screen will return to the Main page.
3. The Pair button in the Pairing tab will now be available to click.



4. Click the Pair button to start pairing LauncherPlus and the Novo device.

5. Once the pairing process is finished, you need to unplug the LauncherPlus and close the utility.

