3.11 NT Minutes

The NT Minutes app allows you to record any actions taken on the NovoTouch screen.



Recording your screen

To record your screen as an MP4 video file using the NT Minutes app:

1. Tap the record button on the NT Minutes main page.



NT Minutes	Record Screen	© View Gallery) Settings		
*	J	00:00:00			
			_	Carlant Storage Factor / Noving NUMProcess	10.00 (01.00.00 in 10.0 (01.00.00

2. The NovoTouch will return to its home screen and a countdown will be shown after which NT Minutes will start recording the screen.



3. Anytime during the recording process you can tap the menu button at the top right corner for the following recording options:





Once you stop the recording process you will have the option to either playback the recorded video, delete the video, or share the video.



You can also view any of the previous screen recordings by tapping the View Gallery tab in the NT Minutes main screen.



Settings

Tap the **Settings** tab in the NT Minutes main screen to configure the following settings: **Bit Rate**, **Resolution**, **Countdown seconds**, **Time limit**, **Size limit**, and **Storage Folder**.

NT Minutes Record Scree	Niew Gallery		
Bit Rate:	4 Mbps +		
Resolution:	1280x720 -		
Countdown seconds:	3		
> Time limit (Hour):	2 *		
Size limit (GB).	2		
Current Storage Folder.	Movies/NT-Minutes *		
Floating ToolBar			
Microphone			
		Current Storage Folder /Movies/NT-Minutes	10.58 GB available / 10.8 GB in total

You are also able to enable/disable the Floating Toolbar and

Microphone during recording process.

Tips: To enable Microphone function, please make sure your USB microphone/webcam have plug into NovoTouch USB port.